

# SmartPlant 3D Equipment v7

## *User Training Exercises*

---


## Table of Contents

<b>Table of Contents .....</b>	<b>2</b>
<b>LAB-1: Placing Parametric Equipment.....</b>	<b>3</b>
<b>LAB-2: Rotating Equipment While Placing / After Placement.....</b>	<b>9</b>
<b>LAB-3: Placing Designed Equipment and Equipment Component.....</b>	<b>12</b>
<b>LAB-4: Placing Equipment with Mate Relationship.....</b>	<b>15</b>
<b>LAB-5: Equipment Modification .....</b>	<b>17</b>
<b>LAB-6: Move / Copy / Paste Equipment.....</b>	<b>18</b>
<b>LAB-7: Placing shapes to Build Designed Equipment .....</b>	<b>20</b>
<b>LAB-8: Placing Nozzles .....</b>	<b>27</b>
<b>LAB-9: Importing Equipment from External Modeler .....</b>	<b>31</b>
<b>LAB-10: Equipment from Shapes and Components .....</b>	<b>33</b>
<b>LAB-11: Placing Equipment from P&amp;ID .....</b>	<b>42</b>


---

## LAB-1: Placing Parametric Equipment

- 1 Remind instructor to remove any existing equipment from your training model
- 2 Open a Session file with Imperial Units  
**Note:** See the common applications labs on how to define a workspace
- 3 Define Workspace to Display U03 and U03 CS in the training plant
- 4 If you are not in the Equipment task, then select Task -> Equipment and Furnishing
- 5 Make sure the Active Permission Group is set to *Equipment*.  
**Note:** Objects that you place directly in the model are assigned to the active permission group. Therefore, **you are responsible of making sure the equipment is assigned to the appropriate Permission Group.**



- 6 Activate PinPoint by Selecting Tools > PinPoint (make sure active Coordinate system is Global)
- 7 Select Place Equipment Command
- 8 Expand the Equipment Folder Process Equipment\Vertical Vessels\Simple Vertical Vessel with Skirt until you see the part SWWSE210-E. Select the part and click the OK button.



9 Equipment Property page is displayed on your screen

10 Key in T-101 for Name

11 Click in the System Field and select 'More...'

**Equipment Properties**


Occurrence | Definition | Connection

Category: Standard

Property	Value
Name	T-101
Name Rule	DefaultNameRule
Description	
System	More ...
Reporting Requirement	To be reported
Reporting Type	To be tracked by material control system
Correlation Status	Not correlated
Correlation Basis	Correlate object

**Note:** Objects that you place directly in the model are associated to a system in the System Hierarchy. Therefore, you are responsible for making sure the equipment is associated to the appropriate System.

- 12 System opens the Select System dialog box. Select the **A2- >U03 -> Equipment** System and Click the OK button.



- 13 Switch to Position and Orientation Category

Occurrence | Definition | Connection

Category: [Preview]

Standard

- Standard
- Position and Orientation
- Insulation and Tracing
- Equipment Dimension
- Equipment Support
- Weight and CG
- Fabrication and Construction
- Surface Treatment and Coating
- System

Property	Value
	T-101
	DefaultNameRule
	Equipment
Reporting Requirement	To be reported
Reporting Type	To be tracked by material control system
Correlation Status	Not correlated
Correlation Basis	Correlate object

14 Key in -21' For Easting, 40' for Northing and 2' for Elevation

15 Switch to Equipment Dimension Category

Note: You can use preview button to understand/relate different dimension variables

Occurrence | Definition | Connection

**Preview**

Category: [Preview]


Equipment Dimension

Property	Value
Dome Height	1 ft 11.62 in
Dome Height 1	
Vessel Diameter	6 ft 6.74 in
Vessel Length	50 ft 0.00 in

16 Change the Vessel Length to 50'


17 OK on the property page

18 Your view should resemble this




19 Select Place Equipment Command

20 Expand the Equipment\Equipment\Mechanical Equipment\Pumps\Pump until you see the part CPump002A8x6-E. Select the part and click the OK button.




- 21 Equipment Property page is displayed on your screen
- 22 Key in P-101 for Name
- 23 Click in the System Field and select 'More...'
- 24 System opens the Select System dialog box. Select the **A2- >U0 3-> Equipment** System and Click the OK button.
- 25 Switch to Position and Orientation Category
- 26 Key in 1' For Easting, 12' for Northing and 2' for Elevation
- 27 OK on the property page
- 28 Your View should resemble this (Beams and Columns turned off here for convenience)






## LAB-2: Rotating Equipment While Placing / After Placement

- 1 Define Workspace to Display U04 and U04 CS
- 2 Activate PinPoint if not already active
- 3 Make Sure Active Coordinate System is set to Global
- 4 Select Place Equipment command from the vertical toolbar to open the Select Equipment Dialog box.
- 5 From Catalog Browser, Select Process\Horizontal Vessels\Storage Tank, Tank 001A IMP E




- 6 Equipment Property page is displayed on your screen
- 7 Key in 40V-101 for Name
- 8 Click in the System Field and select 'More...'
- 9 System opens the Select System dialog box. Select the **A2- > U04 -> Equipment** System and Click the OK button.
- 10 Switch to Position and Orientation Category

11 Key in 98' For Easting, 100' 6" for Northing and 6' for Elevation

Occurrence		Definition	Connection	Relationship	Configuration	Notes
Category:						
Position and Orientation						
Property	Value					
East	98 ft 0.00 in					
North	100 ft 6.00 in					
Elevation	6 ft 0.00 in					
Bearing	90.00 deg					
Pitch	0.00 deg					
Roll	0.00 deg					

12 OK on the property page


13 Your View should resemble this



14 Equipment is Placed and is still selected

15 Up / Down Axis is selected as rotation axis

16 Use Left/Right arrow key to rotate the equipment as shown




Note: While placing equipment, we could have changed the Bearing to 180 to get same rotation angle

---


## LAB-3: Placing Designed Equipment and Equipment Component

---

- 1 Open a Session file with Imperial Units
- 2 Define Workspace to Display U04 and U04 CS
- 3 Activate PinPoint if not already active
- 4 From Ribbon Bar, select more under Coordinate systems
- 5 Expand Coordinate systems and select U04 CS




- 6 Ok on the Select Coordinate System form
- 7 Select Set target to Origin Option
- 8 Select Place Designed Equipment Command
- 9 From Catalog Browser select, \Equipment\Process\Horizontal Vessels\Horizontal Drum with Saddle



- 10 Equipment Property page is displayed on your screen
- 11 Key in 41V-101 for Name
- 12 Click in the System Field and select 'More...'
- 13 System opens the Select System dialog box. Select the **A2- > U04 -> Equipment** System
- 14 Switch to Position and Orientation Category
- 15 Key in 5 For Easting, 8 for Northing and 23' for Elevation
- 16 OK on the property page
- 17 Select Place **Equipment component command** from the vertical toolbar
- 18 If prompted select 41V-101 from WSE
- 19 Locate E245 Horizontal Cylindrical Tank using the tree view. Select the part and click the OK button (Equipment Components\Process Components\Vessel & Equipment Bodies\Horizontal Vessels and Tanks\Simple Horizontal Cylindrical Equipment Component E245)
- 20 Equipment Property page is displayed on your screen

- 21 Key in Tank for Name
- 22 Switch to Position and Orientation Category
- 23 Key in 5 For Easting, 8 for Northing and 23' for Elevation
- 24 Switch to Equipment Dimension Category
- 25 Make the following Changes  
Vessel Center Height : 5' 6"  
Vessel Diameter: 8'  
Vessel Length: 14' 10"
- 26 Change the Category to Equipment Support
- 27 Make the following Changes  
First Support Location: 3'  
Second Support Location: 9'  
Support Thickness: 6" (6 inches)  
Support Length: 7'
- 28 Ok on the form
- 29 Your View should resemble this (only grids and equipment shown)




## LAB-4: Placing Equipment with Mate Relationship

- 1 Open a Session file with Imperial Units
- 2 Define Workspace to Display U04 and U04 CS
- 1 Activate PinPoint if not already active
- 2 Make Sure Active Coordinate System is Set to U04 CS
- 3 Select Place Equipment command from the vertical toolbar to open the select Equipment Dialog box
- 4 Select Pump\_001A\_IMP-E, under Equipment\Mechanical\Pumps\Pump
- 5 Ok on the property page(without making any changes)
- 6 Go to the Equipment ribbon bar and make sure the **U04 -> Equipment** System is set in the **System** drop down list
- 7 Go to the Equipment ribbon bar, and key in **41P-101A** in the Name field



- 8 Go to the PinPoint ribbon bar and key in 30' for East, 5' for North and 0' for El
- 3 In Work Space Explorer, Expand the Co-ordinate System folder, Expand U04 CS folder, Expand EL Axis and Click on EL-0'-0'' to mate the pump with elevation 0'.




- 
- 4 In the Equipment Ribbon Bar, Key in 2' for offset



- 9 Right Click in the View to de-select the Equipment

- 10 Your View should resemble this(only grids and equipment shown)






## LAB-5: Equipment Modification


- 1 Open a Session file with Imperial Units
- 2 Define Workspace to Display U04 and U04 CS
- 3 In workspace explorer expand 40V-101
- 4 Open the properties page for 40V-101 and set the category to Equipment Dimension
- 5 Set the diameter to 8' and the length to 15' and OK
- 6 Set the Locate Filter to "All"
- 7 Select Nozzle STNoz1 under, Equipment 40V-101
- 8 Open property page for nozzle STNoz1
- 9 Change the size to 6" and name to "A"
- 10 Ok on the form
- 11 Select Suction Nozzle under 41P-101A
- 12 Open its Properties page
- 13 Change the size to 8" and name to N1  
Note: After making changes, select Apply instead of OK. You do not need to close the properties page, just click on the next object to open new page. Now you have made changes to suction nozzle, hit apply and select discharge nozzle
- 14 Change the discharge to 6" and name to N2

## LAB-6: Move / Copy / Paste Equipment


- 1 Open a Session file with Imperial Units
- 2 Define Workspace to Display U04 and U04 CS
- 3 Set Coordinate system to Global
- 4 Select Set target to origin option
- 5 Select Equipment 40V-101
- 6 Select Move command from common ribbon bar
- 7 Select Move from option
- 8 Select Nozzle “A” as move from point



- 9 Key in 98' for East, 99' 8" for North and 8' 3" for elevation
- 10 Click in the view to place the equipment at new location
- 11 Set Active Coordinate system to U04 CS
- 12 Select Set target to origin option
- 13 Select pump 41P-101A
- 1 Select Copy command
- 2 When prompted for Reference point, select the Control Point at the bottom left corner




- 3 Select Paste command
- 4 System opens the Paste Special form. U04\Equipment folder in Work Space Explorer is already selected as new system folder
- 5 Uncheck the paste in place option
- 6 Ok on the paste form
- 7 Key in 30' for East, 11' for North and 2' for Elevation.
- 8 Change the name to 41P-101B
- 9 Your view should resemble this(only grids and equipment shown)




## LAB-7: Placing shapes to Build Designed Equipment

- 1 Open a Session file with Imperial Units
- 2 Define Workspace to Display U01 and U01 CS
- 3 Change the Active Coordinate system to U01
- 4 Select set target to origin option
- 5 Select Place Designed Equipment Command
- 6 Select Equipment\Process\Heat Exchangers\Kettle Heat Exchanger
- 1 Equipment Property page is displayed on your screen
- 2 Key in E-102 for Name
- 3 Click in the System Field and select 'More...'
- 4 System opens the Select System dialog box. Select the **A2- > U01 -> Equipment** System and Click the OK button.
- 5 Switch to Position and Orientation Category
- 6 Key in 5 For Easting, -20 for Northing and 6' for Elevation
- 7 Switch to Definition Tab and set the classifications as shown




Property	Value
Part Number	KettleHeatExchanger-1-1
Part Description	
Mirror behavior option	Component may be mirrored
Equipment Classification 0	Process Equipment
Equipment Classification 1	Heat Transfer Equipment
Equipment Classification 2	Shell And Tube Heat Exchanger
Equipment Classification 3	Tubular Reactor
Equipment Classification 4	<undefined value>
Equipment Classification 5	<undefined value>
Equipment Classification 6	<undefined value>


- 8 Select Place shape Command(click on place shape command and hold the left mouse button to display list of shapes). Select Cylinder Shape from the shape options.
- 9 If prompted, select Designed equipment E-102 in WSE
- 10 Enter A=20' and B=6'
- 11 Using PinPoint place the shape at
  - Easting: 5 ft relative to the U01 coordinate system
  - Northing: -20 ft relative to the U01 coordinate system
  - Elevation: 6 ft relative to the U01 coordinate system



- 12 Select Place shape command and select Eccentric Cone from shapes
- 13 Select Designed equipment E-102
- 14 Enter A=3 ft, B=6 ft, C= 4 ft and Click OK
- 15 Change the Relationship to Connect from Mate



16 Select the Point at the East end of the Cylinder





17 Using Arrows Keys rotate the shape so it is Flat on Bottom(Use up arrow key to change rotation axis, left / right arrow key to rotate)




**Elevation View**

- 18 Select Place Shape Command. Select a Cylinder
- 19 Identify E-102
- 20 Enter A=6 and B=4
- 21 Using Connect Place it at the free end of Eccentric cone




- 22 On Pinpoint's Coordinate System pulldown select "Select Graphically"
- 23 Click on the main body of E-102
- 24 Select "Set target to Origin"  from Pinpoint ribbon menu. The target point should appear on the cylinder as shown above
- 25 Select place Rectangular Solid shape
- 26 Enter A=4', B=6' and C=10" (C is 10 inches)
- 27 Using arrow keys rotate the shape as shown




- 28 Place the shape at
- |            |   |
|------------|---|
| Easting:   | 4 ft relative to the first shape coordinate system  |
| Northing:  | 0 ft relative to the first shape coordinate system  |
| Elevation: | -2 ft relative to the first shape coordinate system |
- 29 Place a second Rectangular shape with same dimensions and orientation at
- |            |   |
|------------|---|
| Easting:   | 18 ft relative to the first shape coordinate system |
| Northing:  | 0 ft relative to the first shape coordinate system  |
| Elevation: | -2 ft relative to the first shape coordinate system |






30 Rename all the Shapes under Designed Equipment E-102 as Shown



31 Add Head on Both ends of Equipment as shown.



32 Add 6' long 6' Dia cylinder on Bigger end of Equipment as Maintenance Envelope. ( Turn Maintenance Aspect on under Format View. Apply Surface style rule to make it transparent)



---

## LAB-8: Placing Nozzles

- 1 Open a Session file with Imperial Units
- 2 Define Workspace to Display U01 and U01 CS
- 3 Change the Active Coordinate system to U01
- 4 Select set target to origin option
- 5 Select Place Nozzle Command
- 6 Select Shape(Main Cyl Body) under E-102
- 7 From the Port Type control on the Nozzle Properties form select **Piping Straight Nozzle**.

- 8 Define the following Properties:

PortIndex:	1
NorminalSize:	8
NPDUnitType:	in
Termination Class:	Bolted
Termination SubClass:	Flanged
End Preparation:	RFFE
End Practice:	US Practice
End Standard:	Default
Rating Practice:	US Practice
Pressure Rating:	CL150
Flow Direction:	Flow leaves this port

Scroll down

Nozzle Length:	1 ft
Name:	N1

Switch to the location tab and select Radial in the Placement Type control. Define the following:

N1 = 4 ft  
N2 = 4 ft  
OR1 = 270 degree


**Pipe Nozzle Properties**

Occurrence Location Configuration

☐ OR1 measured to Active Coordinate System North

Placement Type: Radial

Property	Value
N1	4 ft 0.00 in
N2	4 ft 0.00 in
OR1	270.00 deg



OK Cancel Apply

9 Select Place Nozzle Command

10 Select Shape(Main Cyl Body) under E-102

11 From the Port Type control on the Nozzle Properties form select **Piping Straight Nozzle**.

12 Define the following Properties:

PortIndex:	2
NorminalSize:	8
NPDUnitType:	in
Termination Class:	Bolted
Termination SubClass:	Flanged
End Preparation:	RFFE
End Practice:	US Practice
End Standard:	Default

Rating Practice:	US Practice
Pressure Rating:	CL150
Flow Direction:	Flow leaves this port

Scroll down

Nozzle Length:	1 ft
Name:	N2


Switch to the location tab and select Radial in the Placement Type control. Define the following:

N1 = 18 ft

N2 = 4 ft

OR1 = 270 degree

13 Your view should resemble this



14 Activate PinPoint if not already active

15 Define Workspace to Display U04 and U04 CS

16 Change the Active coordinate system to 41V-101(U04\equipment\)

17 Select Set target to origin option


18 Select Place Nozzle Command

19 Select Shape(Tank) under 41V-101

20 From the Port Type control on the Nozzle Properties form select Piping Straight Nozzle.


21 Define the following Properties, 8", RFFE, Length 1', Name N1 (Define Rest of the properties as previous labs)

- 22 From Location Tab, select Position by point option. Ok on the form
- 23 Key in East 1, North 0 and Elevation 5'
- 24 Rotate the Nozzle using arrow keys. Make sure RFFE is on top
- 25 Click to place the nozzle
- 26 Your View Should Resemble this (only equipment and grids shown)



Select Place nozzle command

- 27 Select same Tank again
- 28 Define the following Properties, 8", RFFE, Length 1', Name N2 (Define Rest of the properties as previous labs)
- 29 From Location Tab, select Position by point option. Ok on the form
- 30 Key in East 13 6", North 0 and Elevation -4' 10"
- 31 Rotate the Nozzle using arrow keys. Make sure RFFE is at the bottom
- 32 Click to place the nozzle
- 33 Your View Should Resemble this




---

## LAB-9: Importing Equipment from External Modeler

---

- 1 Ask instructor for Tank\_Shape.sat file
- 2 Open a Session file with Imperial Units
- 3 Define Workspace to Display U02 and U02 CS
- 4 Activate PinPoint if not already active
- 5 Change the active coordinate system to U02 CS
- 6 Select Set target to origin option
- 7 Select Place Designed Equipment Command
- 8 From Catalog select \Equipment\Process\Horizontal Vessels\Horizontal Drum with Saddle
- 9 OK on the property page
- 10 Key in East 15', North 30' and Elevation 0
- 11 Left click to place the equipment
- 12 Change the System to U02, Equipment
- 13 Change the Name to DR-100 (Press ENTER to force the name update)
- 14 Select the place imported shape from file command on the vertical toolbar.
- 15 If prompted, select DR-100 from the workspace explorer
- 16 Select the Tank\_Shape.sat file from specified location
- 17 In the Display aspects dialog, select Simple Physical and click OK.
- 18 Key in East 15', North 30' and Elevation 0
- 19 Change the name of tank to Drum Body

20 Change the Active coordinate system to DR-100



21 Select Set target to origin option

22 Select place Nozzle Command

23 Select Drum Body as shape to add nozzle to

24 Define the following Properties, 8", RFFE, Length 1', Name N1 (Define Rest of the properties as previous labs)


25 From Location Tab, select Position by point option. Ok on the form

26 Key in East -2' 6", North 8' and Elevation 9'.

27 Rotate the Nozzle so RFFE is on top

28 Click in the view to place the nozzle

29 Your View Should Resemble this






## LAB-10: Equipment from Shapes and Components


NOTE: These are not detailed steps. Just an outline of things to consider

- 1 Open a Session file with Imperial Units
- 2 Define Workspace to Display U02 and U02 CS
- 3 Activate PinPoint if not already active
- 4 Change the active coordinate system to U02 CS



- 5 Select Place Designed Equipment Command
- 6 Select \Equipment\Process\Vertical Vessels\Simple Vertical Vessel with Skirt and click OK.
- 7 Property page is displayed on your screen
- 8 Key in VS-102 for Name
- 9 Change the system to U02 -> Equipment System


- 10 OK on the property page
- 11 Place the design equipment at E -25, N -15 and EL 2
- 12 Select Place Shape command. Select the cylinder shape.
- 13 If prompted, select VS-102 as designed equipment
- 14 Place a Cylinder as base with dimensions A=6”(inches) and B=10’
- 15 Place the shape at E -25, N - 15 and EL 2
- 16 Rotate the shape so that the place point is at the Bottom
- 17 Change the name to Base
- 18 Select Place Equipment component command. Select VS-102 (if prompted)
- 19 Select E(210)-Vertical tank under \Equipment Components\Process Components\Vessel & Equipment Bodies\Vertical Vessels and Tanks\Simple Vertical Cylindrical Equipment Skirt Component (E210)
- 20 Property page is displayed on the screen
- 21 Change the name to Vertical Tank
- 22 Switch to Equipment Dimension Category
- 23 Make following changes



Property	Value
Vessel Height	30 ft 0.00 in
Vessel Diameter	5 ft 0.00 in
Vessel Start Height	9 ft 0.00 in

- 24 Switch to Equipment Support Category


25 Make following changes

Category: Equipment Support 

Property	Value
Skirt Top Diameter	5 ft 0.00 in
Skirt Bottom Diameter	9 ft 0.00 in
Skirt Height	9 ft 0.00 in
Skirt Diameter	


26 Switch to Position and Orientation Category

27 Make following changes and OK on the form

Category: Position and Orientation 

Property	Value
East	-25 ft 0.00 in
North	-15 ft 0.00 in
Elevation	2 ft 6.00 in
Bearing	90.00 deg
Pitch	0.00 deg
Roll	0.00 deg

28 Place All nozzles by selecting DP2 under Vertical Tank. Nozzle Properties are detailed below



**Nozzle: N1**

Nozzle Length: 1'

Name: N1

Pipe Nozzle Properties

Occurrence | Location | Configuration

Category: Standard Port Type: Piping Straight Nozzle

Property	Value
PortIndex	1
NominalSize	6
NpdUnitType	in
Termination Class	Bolted
Termination SubClass	Flanged
End Preparation	Raised-face flanged end
Schedule Practice	US Practice
Schedule Thickness	S-XS
Piping Point Basis	Undefined
End Practice	US Practice


OK Cancel Apply

Occurrence | **Location** | Configuration |

☐ OR1 measured to Active Coordinate System North

Placement Type: **Axial**

Property	Value
N1	32 ft 0.00 in
N2	1 ft 0.00 in
OR1	270.00 deg



**Nozzle: N2**

Nozzle Length: 1' 6"      Name: N2

**Pipe Nozzle Properties**

Occurrence | Location | Configuration |

Category: **Standard**

Port Type: **Piping Straight Nozzle**

Property	Value
PortIndex	2
NominalSize	6
NpdUnitType	in
Termination Class	Bolted
Termination SubClass	Flanged
End Preparation	Raised-face flanged end
Schedule Practice	US Practice
Schedule Thickness	S-XS
Piping Point Basis	Undefined
End Practice	US Practice


**Pipe Nozzle Properties**

Occurrence | **Location** | Configuration

☐ OR1 measured to Active Coordinate System North

Placement Type: Radial

Property	Value
N1	12 ft 0.00 in
N2	3 ft 0.00 in
OR1	270.00 deg



OK Cancel Apply

**Nozzle: N3**

Nozzle Length: 2'

Name: N3

**Pipe Nozzle Properties**

Occurrence | Location | **Configuration**

Category: Standard

Port Type: Piping Straight Nozzle

Property	Value
PortIndex	3
NominalSize	8
NpdUnitType	in
Termination Class	Bolted
Termination SubClass	Flanged
End Preparation	Raised-face flanged end
Schedule Practice	US Practice
Schedule Thickness	S-XS
Piping Point Basis	Undefined
End Practice	US Practice


**Pipe Nozzle Properties**

Occurrence | **Location** | Configuration

☐ OR1 measured to Active Coordinate System North

Placement Type: **Tangential**

Property	Value
N1	8 ft 0.00 in
N2	3 ft 6.00 in
N3	0 ft 0.00 in
OR1	225.00 deg




**Nozzle: N4**

Occurrence | Location | Configuration

Category: **Standard**

Port Type: **Piping Elbow Nozzle**

Property	Value
PortIndex	4
NominalSize	6
NpdUnitType	in
Termination Class	Bolted
Termination SubClass	Flanged
End Preparation	Raised-face flanged end




Property	Value
Schedule Practice	US Practice
Schedule Thickness	S-XS
Piping Point Basis	Undefined
End Practice	US Practice
End Standard	Default
Rating Practice	US Practice

Property	Value
Pressure Rating	CL150
Flow Direction	Undefined
Flange Or Hub OutsideDiameter	0 ft 11.00 in
WallThickness Or GrooveSetback	0 ft 0.00 in
Raised Face Or Socket Diameter	0 ft 8.50 in
Flange Or HubThickness	0 ft 1.00 in


Property	Value
Nozzle Length	2 ft 0.00 in
Bend Length	2 ft 0.00 in
Bend Radius	2 ft 0.00 in
Name	N4
Correlation Status	Not correlated
Correlation Basis	Correlate object






## *Adding Insulation Aspect*

Add 3" insulation to the main Vessel Body( to equipment component, not design equipment)  
Define a Surface Style Rule to make Insulation Translucent




## LAB-11: Placing Equipment from P&ID

- 1 Open a session file and define a filter for your workspace that includes the U02 and its coordinate system.
- 2 Activate PinPoint if not already active
- 3 Change the coordinate system to U02 CS
- 4 Select Set target to origin option
- 5 Go to Smartplant > View P&ID
- 6 Select INT01 from the PID list, Select open button
- 7 PID Viewer opens up in a Window
- 8 Select Equipment T-162 from PID




- 9 Select Place Equipment Command

- 10 System opens up the Catalog Browser, and Simple Vertical Vessel is selected. Ok on the form (if not, select the equipment shown below)



- 11 System Opens up Compare design Basis form. This reflects difference between Model and PID



- 12 Select Update on the form. Click close

- 13 Software displays the properties page

14 System fills the name from PID (T-162)

15 Change the system to U02 > Equipment

16 Change the Category to Equipment Dimension and make following changes

**Equipment Properties**

Occurrence | Definition | Connection | Relationship | Configuration | Notes

Category:  
Equipment Dimension

Property	Value
Vessel Height	35 ft 0.00 in
Vessel Diameter	6 ft 0.00 in
Vessel Start Height	9 ft 0.00 in

17 Switch to Equipment Support Category, Skirt top Dia 6', Bottom Dia 11', Skirt height 9'

18 Switch to Platform Category and make following changes

Occurrence | Definition | Connection | Relationship | Configuration | Notes


Category:  
Platform

Property	Value
Platform Radius	
Clearance from Vessel	
Opening Diameter	
Platform Width	2 ft 6.00 in
Platform Height	0 ft 3.00 in
Platform Angle	180.00 deg

19 Switch to Position and Orientation category

20 Place the Equipment at E 10, N -35, EL 2

- 21 Select the Nozzle, Vessel Noz1 at the top of the Equipment T-162 in the model.
- 22 Select Smartplant, Correlate with Design Basis option
- 23 System prompts from Item from PID
- 24 Select Nozzle B2, at the top in PID Viewer



- 25 Select Update from Compare design basis form. This will change the nozzle properties in the model to match PID
- 26 Close the form
- 27 Select Nozzle B2 in WSE and open its properties page
- 28 Change its length to 1' 6"
- 29 Select the Nozzle, Vessel Noz2 on Equipment T-162 in the model.


- 30 Select Smartplant, Correlate with Design Basis option
- 31 System prompts from Item from PID
- 32 Select Nozzle P2, in PID Viewer
- 33 Select Update from Compare design basis form. This will change the nozzle properties in the model to match PID
- 34 Close the form
- 35 Select Nozzle P2 in WSE and open its properties page
- 36 Change its length to 1' 6"
- 37 Switch to location tab and change N1 to 33'. Ok on the form
- 38 Select the Nozzle, Vessel Noz3 on Equipment T-162 in the model.
- 39 Select Smartplant, Correlate with Design Basis option
- 40 System prompts from Item from PID
- 41 Select Nozzle A5, in PID Viewer
- 42 Select Update from Compare design basis form. This will change the nozzle properties in the model to match PID
- 43 Close the form
- 44 Select Nozzle A5 in WSE and open its properties page
- 45 Change its length to 1' 6"
- 46 Switch to location tab and change N1 to 32'. Ok on the form
- 47 Select nozzle T3 in PID viewer
- 48 Select place nozzle command in the model
- 49 Select DP2, under T-162 in WSE, as the shape to add nozzle to.
- 50 Software displays Place Nozzle form with all Nozzle data already filled from PID. Change the length to 1'
- 51 Switch to Location tab, and make following changes

Occurrence
Location
Configuration


☐ OR1 measured to Active Coordinate System North

Placement Type  
 Radial

Property	Value
N1	15 ft 0.00 in
N2	3 ft 6.00 in
OR1	270.00 deg




Place all the Nozzles from PID on EQP T-162.



- 52 Change your Workspace to Display all Filter
- 53 Expand U04, Equipment and select 41P-101A.
- 54 Select Copy command.
- 55 Select Top of Discharge nozzle as Reference point.
- 56 Select Paste command. Check Paste in Place option and Ok on the form
- 57 Select New Equipment (copied equipment) if not already selected
- 58 Open properties page
- 59 Change system to U02, equipment.
- 60 Switch to position and orientation category
- 61 Change the coordinates to E 25, N -50 and EL 3 WRT U02 CS
- 62 Select the copied equipment and go to Smartplant, Correlate with Design Basis.
- 63 System prompts for Select PID item to be correlated
- 64 In PID viewer select pump P-162. System displays Compare with Design Basis form. Select Update.
- 65 Select nozzle N1 under pump, select Smartplant compare design basis.
- 66 Update on the form. Close the form. This should turn nozzle green.
- 67 Update nozzle N2 same way. When done. The equipment and nozzles should turn green in the PID. If Equipment is not green, Select the equipment and select Compare with Design Basis. Select update. This will turn Equipment and Nozzles green in PID.





**FUTURE LABS:**

- 1 MORE PRACTICE WITH RELATIONSHIPS ON THE FLY AND AFTER PLACEMENT
- 2 MODEL OTHER DISCIPLINES EQP: ELECTRICAL, HVAC
- 3 PLACING CONN PORTS OTHER THAN PIPING
- 4 REFERENCING DGN AND ADDING CON PORTS TO SAT OR DGN REF'S